

System.Security.Permissions.EnvironmentPermissionAttribute Class

```
[ILASM]
.class public sealed serializable
EnvironmentPermissionAttribute extends
System.Security.Permissions.CodeAccessSecurityAttribute

[C#]
public sealed class EnvironmentPermissionAttribute :
CodeAccessSecurityAttribute
```

Assembly Info:

- *Name:* mscorlib
- *Public Key:* [00 00 00 00 00 00 00 00 04 00 00 00 00 00 00]
- *Version:* 1.0.x.x
- *Attributes:*
 - CLSCompliantAttribute(true)

Type Attributes:

- AttributeUsageAttribute(AttributeTargets.Assembly | AttributeTargets.Class | AttributeTargets.Struct | AttributeTargets.Constructor | AttributeTargets.Method, AllowMultiple=true, Inherited=false)

Summary

Used to declaratively specify security actions to control access to environment variables.

Inherits From: System.Security.Permissions.CodeAccessSecurityAttribute

Library: BCL

Thread Safety: All public static members of this type are safe for multithreaded operations. No instance members are guaranteed to be thread safe.

Description

Environment variable names are case-insensitive. Multiple environment variable names are specified by separating the names using the **System.IO.Path.PathSeparator** string.

[Note: The level of access to one or more environment variables is specified using the members of the current instance. For example, to specify read permissions for an environment variable, set the

1 **System.Security.Permissions.EnvironmentPermissionAttribute.**
2 **Read** property equal to the name of the environment variable.

3
4 The security information declared by a security attribute is stored in
5 the metadata of the attribute target, and is accessed by the system at
6 run-time. Security attributes are used for declarative security only. For
7 imperative security, use the corresponding permission class,
8 **System.Security.Permissions.EnvironmentPermission.**

9
10 The allowable
11 **System.Security.Permissions.EnvironmentPermissionAttribute**
12 targets are determined by the
13 **System.Security.Permissions.SecurityAction** passed to the
14 constructor.]

15 **Example** 16

17 The following example shows a declarative request for the ability to
18 read the specified environment variables. The
19 **System.Security.Permissions.SecurityAction.RequestMinimum**
20 security action indicates that this is the minimum permission required
21 for the target assembly to be able to execute.

22
23 [assembly:EnvironmentPermissionAttribute(SecurityAction.RequestMinimum, Read="COMPUTERNAME;USERNAME;USERDOMAIN")]
24

25
26 The following example shows how to demand that the calling code has
27 unrestricted access to all environment variables. Demands are typically
28 made in managed libraries to protect methods or classes from
29 malicious code.

30
31 [EnvironmentPermissionAttribute(SecurityAction.Demand,
32 Unrestricted=true)]

33

EnvironmentPermissionAttribute(System. Security.Permissions.SecurityAction) Constructor

```
[ILASM]  
public rtspecialname specialname instance void  
.ctor(valuetype System.Security.Permissions.SecurityAction  
action)  
  
[C#]  
public EnvironmentPermissionAttribute(SecurityAction  
action)
```

Summary

Constructs and initializes a new instance of the **System.Security.Permissions.EnvironmentPermissionAttribute** class with the specified **System.Security.Permissions.SecurityAction** value.

Parameters

Parameter	Description
<i>action</i>	A System.Security.Permissions.SecurityAction value.

Exceptions

Exception	Condition
System.ArgumentException	<i>action</i> is not a valid System.Security.Permissions.SecurityAction value.

EnvironmentPermissionAttribute.CreatePermission() Method

```
[ILASM]
.method public hidebysig virtual class
System.Security.IPermission CreatePermission()

[C#]
public override IPermission CreatePermission()
```

Summary

Returns a new **System.Security.Permissions.EnvironmentPermission** that contains the security information of the current instance.

Return Value

A new **System.Security.Permissions.EnvironmentPermission** object with the security information of the current instance.

Description

[Note: Applications typically do not call this method; it is intended for use by the system.

The security information described by a security attribute is stored in the metadata of the attribute target, and is accessed by the system at run-time. The system uses the object returned by this method to convert the security information of the current instance into the form stored in metadata.

This method overrides **System.Security.Permissions.SecurityAttribute.CreatePermission.**

EnvironmentPermissionAttribute.All

Property

```
[ILASM]  
.property string All { public hidebysig specialname  
instance void set_All(string value) }
```

```
[C#]  
public string All { set; }
```

Summary

Sets the environment variables for which full access is secured.

Property Value

A **System.String** containing one or more environment variables for which full access is secured.

Description

This property is write-only.

Multiple environment variable names are specified by separating the names using the **System.IO.Path.PathSeparator** string. Environment variable names are case-insensitive.

[*Note:* The security action passed to the constructor of the current instance determines how the specified environment variables are secured. For example, if the action is **System.Security.Permissions.SecurityAction.RequestMinimum**, then the target of the current instance requires full access to the specified variables in order to execute. If the action is **System.Security.Permissions.SecurityAction.RequestRefuse**, then the system does not allow the target any access to the specified variables.]

1 EnvironmentPermissionAttribute.Read

2 Property

```
3 [ILASM]
4 .property string Read { public hidebysig specialname
5 instance string get_Read() public hidebysig specialname
6 instance void set_Read(string value) }

7 [C#]
8 public string Read { get; set; }
```

9 Summary

10 Gets or sets the environment variables for which read access is
11 secured.

12 Property Value

13

14 A **System.String** containing one or more environment variables for
15 which read access is secured.

16 Description

17 Multiple environment variable names are specified by separating the
18 names using the **System.IO.Path.PathSeparator** string.
19 Environment variable names are case-insensitive.

20

21 [Note: The security action passed to the constructor of the current
22 instance determines how the specified environment variables are
23 secured. For example, if the action is
24 **System.Security.Permissions.SecurityAction.RequestMinimum**,
25 then the target of the current instance requires read access to the
26 specified variables in order to execute. If the action is
27 **System.Security.Permissions.SecurityAction.RequestRefuse**,
28 then the system does not allow the target to read the specified
29 variables.]

30

EnvironmentPermissionAttribute.Write Property

```
[ILASM]
.property string Write { public hidebysig specialname
instance string get_Write() public hidebysig specialname
instance void set_Write(string value) }

[C#]
public string Write { get; set; }
```

Summary

Gets or sets the environment variables for which write access is secured.

Property Value

A **System.String** containing one or more environment variables for which write access is secured.

Description

Multiple environment variable names are specified by separating the names using the **System.IO.Path.PathSeparator** string. Environment variable names are case-insensitive.

[*Note:* The security action passed to the constructor of the current instance determines how the specified environment variables are secured. For example, if the action is **System.Security.Permissions.SecurityAction.RequestMinimum**, then the target of the current instance requires write access to the specified variables in order to execute. If the action is **System.Security.Permissions.SecurityAction.RequestRefuse**, then the system does not allow the target to write the specified variables.]