

System.MemberAccessException Class

```
[ILASM]
.class public serializable MemberAccessException extends
System.SystemException

[C#]
public class MemberAccessException: SystemException
```

Assembly Info:

- *Name:* mscorlib
- *Public Key:* [00 00 00 00 00 00 00 00 04 00 00 00 00 00 00]
- *Version:* 1.0.x.x
- *Attributes:*
 - CLSCompliantAttribute(true)

Summary

System.MemberAccessException is the base class for exceptions that occurs when an attempt to locate or access a type member fails.

Inherits From: System.SystemException

Library: RuntimeInfrastructure

Thread Safety: All public static members of this type are safe for multithreaded operations. No instance members are guaranteed to be thread safe.

Description

[*Note:* **System.MemberAccessException** exceptions are typically thrown by the system when members in a class library have been changed or removed, and an assembly that references the class library has not been recompiled.

The Base Class Library includes the following derived types:

- **System.FieldAccessException**
- **System.MethodAccessException**
- **System.MissingMemberException**

When appropriate, use these types instead of **System.MemberAccessException.**]

1 MemberAccessException() Constructor

```
2 [ILASM]  
3 public rtspecialname specialname instance void .ctor()  
4 [C#]  
5 public MemberAccessException()
```

6 Summary

7 Constructs and initializes a new instance of the
8 **System.MemberAccessException** class.

9 Description

10 This constructor initializes the
11 **System.MemberAccessException.Message** property of the new
12 instance to a system-supplied message that describes the error, such
13 as "Cannot access member." This message takes into account the
14 current system culture.

15
16 The **System.MemberAccessException.InnerException** property of
17 the new instance is initialized to **null**.

18

1 MemberAccessException(System.String) 2 Constructor

```
3 [ILASM]  
4 public rtspecialname specialname instance void .ctor(string  
5 message)  
  
6 [C#]  
7 public MemberAccessException(string message)
```

8 Summary

9 Constructs and initializes a new instance of the
10 **System.MemberAccessException** class.

11 Parameters

12
13

Parameter	Description
<i>message</i>	A System.String that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.

14

15 Description

16 This constructor initializes the
17 **System.MemberAccessException.Message** property of the new
18 instance using *message*. If *message* is **null**, the
19 **System.MemberAccessException.Message** property is initialized to
20 the system-supplied message provided by the constructor that takes
21 no arguments.

22

23 The **System.MemberAccessException.InnerException** property of
24 the new instance is initialized to **null**.

25

1 MemberAccessException(System.String, 2 System.Exception) Constructor

```
3 [ILASM]  
4 public rtspecialname specialname instance void .ctor(string  
5 message, class System.Exception inner)  
  
6 [C#]  
7 public MemberAccessException(string message, Exception  
8 inner)
```

9 Summary

10 Constructs and initializes a new instance of the
11 **System.MemberAccessException** class.

12 Parameters

13
14

Parameter	Description
<i>message</i>	A System.String that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.
<i>inner</i>	An instance of System.Exception that is the cause of the current exception. If <i>inner</i> is not a null reference, then the current System.Exception was raised in a catch block handling <i>inner</i> .

15

16 Description

17 This constructor initializes the
18 **System.MemberAccessException.Message** property of the new
19 instance using *message* and the
20 **System.MemberAccessException.InnerException** property using
21 *inner*. If *message* is **null**, the
22 **System.MemberAccessException.Message** property is initialized to
23 the system-supplied message provided by the constructor that takes
24 no arguments.

25

26 [Note: For more information on inner exceptions, see
27 **System.Exception.InnerException**.]

28