

System.NullReferenceException Class

```
[ILASM]
.class public serializable NullReferenceException extends
System.SystemException

[C#]
public class NullReferenceException: SystemException
```

Assembly Info:

- *Name:* mscorlib
- *Public Key:* [00 00 00 00 00 00 00 00 04 00 00 00 00 00 00]
- *Version:* 1.0.x.x
- *Attributes:*
 - CLSCompliantAttribute(true)

Summary

Represents the error that occurs when there is an attempt to dereference a null object reference.

Inherits From: System.SystemException

Library: BCL

Thread Safety: All public static members of this type are safe for multithreaded operations. No instance members are guaranteed to be thread safe.

Description

[*Note:* Applications throw the **System.ArgumentNullException** rather than **System.NullReferenceException**.

The following IL instructions throw **System.NullReferenceException**:

- callvirt
- cpblk
- cpobj
- ldelema
- ldelem.<type>

- 1 • ldfld
- 2 • ldflda
- 3 • ldind.<type>
- 4 • ldlen
- 5 • stelem.<type>
- 6 • stind.<type>
- 7 • stfld
- 8 • throw
- 9 • unbox
- 10 • initblk
- 11]

12 Example

13

14 The following example demonstrates an error that causes a
15 **System.NullReferenceException** exception.

```
16 [C#  
17  
18 using System;  
19 public class Ints {  
20     public int[] myInts;  
21 }  
22 public class NullRefExample {  
23     public static void Main() {  
24         Ints ints = new Ints();  
25         try {  
26             int i = ints.myInts[0];  
27         }  
28         catch(NullReferenceException e) {  
29             Console.WriteLine("Caught error: {0}.", e);  
30         }  
31     }  
32 }  
33
```

34 The output is

```
35  
36 Caught error: System.NullReferenceException: Object  
37 reference not set to an instance of an object.
```

```
1      at NullRefExample.Main().  
2  
3
```

1 NullReferenceException() Constructor

```
2 [ILASM]  
3 public rtspecialname specialname instance void .ctor()  
4 [C#]  
5 public NullReferenceException()
```

6 Summary

7 Constructs and initializes a new instance of the
8 **System.NullReferenceException** class.

9 Description

10 This constructor initializes the
11 **System.NullReferenceException.Message** property of the new
12 instance to a system-supplied message that describes the error, such
13 as "The value 'null' was found where an instance of an object was
14 required." This message takes into account the current system culture.
15
16 The **System.NullReferenceException.InnerException** property is
17 initialized to **null**.

18

1 NullReferenceException(System.String) 2 Constructor

```
3 [ILASM]  
4 public rtspecialname specialname instance void .ctor(string  
5 message)  
  
6 [C#]  
7 public NullReferenceException(string message)
```

8 Summary

9 Constructs and initializes a new instance of the
10 **System.NullReferenceException** class.

11 Parameters

12
13

Parameter	Description
<i>message</i>	A System.String that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.

14

15 Description

16 This constructor initializes the
17 **System.NullReferenceException.Message** property of the new
18 instance using *message*. If *message* is **null**, the
19 **System.NullReferenceException.Message** property is initialized to
20 the system-supplied message provided by the constructor that takes
21 no arguments. The
22 **System.NullReferenceException.InnerException** property is
23 initialized to **null**.

24

1 NullReferenceException(System.String, 2 System.Exception) Constructor

```
3 [ILASM]  
4 public rtspecialname specialname instance void .ctor(string  
5 message, class System.Exception innerException)  
  
6 [C#]  
7 public NullReferenceException(string message, Exception  
8 innerException)
```

9 Summary

10 Constructs and initializes a new instance of the
11 **System.NullReferenceException** class.

12 Parameters

13
14

Parameter	Description
<i>message</i>	A System.String that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.
<i>innerException</i>	An instance of System.Exception that is the cause of the current Exception. If <i>innerException</i> is non-null, then the current Exception was raised in a catch block handling <i>innerException</i> .

15
16

16 Description

17 This constructor initializes the
18 **System.NullReferenceException.Message** property of the new
19 instance using *message*, and the
20 **System.NullReferenceException.InnerException** property using
21 *innerException*. If *message* is **null**, the
22 **System.NullReferenceException.Message** property is initialized to
23 the system-supplied message provided by the constructor that takes
24 no arguments.

25
26
27

[*Note:* For information on inner exceptions, see
System.Exception.InnerException.]

28