

1 System.TypeUnloadedException Class

```
2 [ILAsm]  
3 .class public serializable TypeUnloadedException extends  
4 System.SystemException  
  
5 [C#]  
6 public class TypeUnloadedException: SystemException
```

7 Assembly Info:

- 8 • *Name:* mscorlib
- 9 • *Public Key:* [00 00 00 00 00 00 00 00 04 00 00 00 00 00 00]
- 10 • *Version:* 2.0.x.x
- 11 • *Attributes:*
 - 12 ○ CLSCompliantAttribute(true)

13 Summary

14 Represents the error that occurs when there is an attempt to access a `System.Type` that
15 has been unloaded.

16 Inherits From: System.SystemException

17

18 **Library:** RuntimeInfrastructure

19

20 **Thread Safety:** All public static members of this type are safe for multithreaded operations.
21 No instance members are guaranteed to be thread safe.

22

1 TypeUnloadedException() Constructor

```
2 [ILAsm]  
3 public rtspecialname specialname instance void .ctor()  
4 [C#]  
5 public TypeUnloadedException()
```

6 Summary

7 Constructs and initializes a new instance of the `System.TypeUnloadedException` class.

8 Description

9 This constructor initializes the `System.TypeUnloadedException.Message` property of the
10 new instance to a system-supplied message that describes the error, such as "Type has
11 been unloaded." This message takes into account the current system culture.
12

13 The `System.TypeUnloadedException.InnerException` property of the new instance is
14 initialized to null.

15

1 TypeUnloadedException(System.String)

2 Constructor

```
3 [ILAsm]  
4 public rtspecialname specialname instance void .ctor(string message)  
5 [C#]  
6 public TypeUnloadedException(string message)
```

7 Summary

8 Constructs and initializes a new instance of the `System.TypeUnloadedException` class.

9 Parameters

Parameter	Description
<i>message</i>	A <code>System.String</code> that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.

10

11 Description

12 This constructor initializes the `System.TypeUnloadedException.Message` property of the
13 new instance using *message*. If *message* is null, the
14 `System.TypeUnloadedException.Message` property is initialized to the system-supplied
15 message provided by the constructor that takes no arguments.

16

17 The `System.TypeUnloadedException.InnerException` property of the new instance is
18 initialized to null.

19

1 TypeUnloadedException(System.String, 2 System.Exception) Constructor

```
3 [ILAsm]  
4 public rtspecialname specialname instance void .ctor(string message, class  
5 System.Exception innerException)  
  
6 [C#]  
7 public TypeUnloadedException(string message, Exception innerException)
```

8 Summary

9 Constructs and initializes a new instance of the System.TypeUnloadedException class.

10 Parameters

Parameter	Description
<i>message</i>	A System.String that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.
<i>innerException</i>	An instance of System.Exception that is the cause of the current exception. If <i>innerException</i> is non-null, then the current Exception was raised in a catch block handling <i>innerException</i> .

11 12 Description

13 This constructor initializes the System.TypeUnloadedException.Message property of the
14 new instance using *message* and the System.TypeUnloadedException.InnerException
15 property using *innerException*. If *message* is null, the
16 System.TypeUnloadedException.Message property is initialized to the system-supplied
17 message provided by the constructor that takes no arguments.

18
19 [Note: For more information on inner exceptions, see
20 System.Exception.InnerException.]
21
22

23