

1 System.NotImplementedException Class

```
2 [ILAsm]  
3 .class public serializable NotImplementedException extends  
4 System.SystemException  
  
5 [C#]  
6 public class NotImplementedException : SystemException
```

7 Assembly Info:

- 8 • *Name:* mscorlib
- 9 • *Public Key:* [00 00 00 00 00 00 00 00 04 00 00 00 00 00 00]
- 10 • *Version:* 2.0.x.x
- 11 • *Attributes:*
 - 12 ○ CLSCompliantAttribute(true)

13 Summary

14 Represents the error that occurs when a requested operation is not implemented for a
15 given type.

16 Inherits From: System.SystemException

17

18 **Library:** BCL

19

20 **Thread Safety:** All public static members of this type are safe for multithreaded operations.
21 No instance members are guaranteed to be thread safe.

22

23 Description

24 [Note: A number of the types and constructs, specified elsewhere in this Standard, are
25 not required of CLI implementations that conform only to the Kernel Profile. For
26 example, the floating-point feature set consists of the floating-point data types
27 System.Single and System.Double. If support for these is omitted from an
28 implementation, any attempt to reference a signature that includes the floating-point
29 data types results in an exception of type System.NotImplementedException.

30

31]

32

1 NotImplementedException() Constructor

```
2 [ILAsm]  
3 public rtspecialname specialname instance void .ctor()  
4 [C#]  
5 public NotImplementedException()
```

6 Summary

7 Constructs and initializes a new instance of the `System.NotImplementedException`
8 class.

9 Description

10 This constructor initializes the `System.NotImplementedException.Message` property of
11 the new instance to a system-supplied message that describes the error. This message
12 takes into account the current system culture.

13
14 The `System.NotImplementedException.InnerException` property is initialized to `null`.

15

1 NotImplementedException(System.String) 2 Constructor

```
3 [ILAsm]  
4 public rtspecialname specialname instance void .ctor(string message)  
5 [C#]  
6 public NotImplementedException(string message)
```

7 Summary

8 Constructs and initializes a new instance of the `System.NotImplementedException`
9 class.

10 Parameters

Parameter	Description
<i>message</i>	A <code>System.String</code> that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.

11 12 Description

13 This constructor initializes the `System.NotImplementedException.Message` property of
14 the new instance using *message*. If *message* is null, the
15 `System.NotImplementedException.Message` property is initialized to the system-
16 supplied message provided by the constructor that takes no arguments. The
17 `System.NotImplementedException.InnerException` property is initialized to null.

18

1 NotImplementedException(System.String, 2 System.Exception) Constructor

```
3 [ILAsm]  
4 public rtspecialname specialname instance void .ctor(string message, class  
5 System.Exception innerException)  
  
6 [C#]  
7 public NotImplementedException(string message, Exception innerException)
```

8 Summary

9 Constructs and initializes a new instance of the System.NotImplementedException
10 class.

11 Parameters

Parameter	Description
<i>message</i>	A System.String that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.
<i>innerException</i>	An instance of System.Exception that is the cause of the current Exception. If <i>innerException</i> is non-null, then the current Exception was raised in a catch block handling <i>innerException</i> .

12 13 Description

14 This constructor initializes the System.NotImplementedException.Message property of
15 the new instance using *message*, and the
16 System.NotImplementedException.InnerException property using *innerException*. If
17 *message* is null, the System.NotImplementedException.Message property is initialized
18 to the system-supplied message provided by the constructor that takes no arguments.

19
20 [Note: For information on inner exceptions, see System.Exception.InnerException.]
21
22

23